

# Bulk Plant Freight

This program allows the operator to create or maintain freight calculation records to be used when transporting fuel from the terminal(s) to the Bulk Location.

Bulk Plant Freight

Save Undo Close

Details

Remove

Export

View

Filter (F3)

<input type="checkbox"/>	Tariff Type	Company	Zip Code	Category	Freight Ty	Fixed Ship	Freight An	Freight-In	Freight-Out	Freight Mi	Minimum	Minimum	Surcharge
<input type="checkbox"/>	Intrast...	0002 - ...	47305	TR-Cat...	Rate		0.00000	10.00	0.00	0.00	0.00	0.00	0.00
<input type="checkbox"/>	Intrast...	0001 - ...	47305	TR-Cat...	Miles		0.00000	0.00	0.00	30.00	0.00	0.00	0.00
<input type="checkbox"/>	IN Only	0000 - ...	46815	GAS	Rate		0.00000	0.00	0.05	0.00	0.00	0.00	0.00
<input type="checkbox"/>	Intrast...	0004 - ...	46815	GAS	Miles		0.00000	0.00	0.00	100.00	0.00	0.00	0.00
<input type="checkbox"/>	Multi-S...	0001 - ...	46815	GAS	Rate		0.00000	1.25	1.5	0.00	0.00	0.00	0.00
<input type="checkbox"/>							0.00000	0.00	0.0	0.00	0.00	0.00	0.00

6.8s

Ready

Refresh

Open Bulk Plant Freight screen from **Transports | Bulk Plant Freight** .The menu will open up displaying all the existing freight calculation records.

Tank Management

Card Fueling

Store

CRM

Help Desk

Document Management

Transports

Meter Billing

Quality

Warehouse

Motor Fuel Tax Forms

Patronage

Transports

Activities

Transport Loads

Quote

Rack Price

Batch Posting

Automated Process Status BOL

Automated Process Status BOL Image

Automated Process Status Rack Price

Automated Process Status Quote

Create

New Quote

New Rack Price

New Transport Load

Maintenance

Bulk Plant Freight

Combo Freight

Cross Reference - BOL Import

Cross Reference - Vendor Invoice Import

Quote Price Adjustment

Tax Group Override

#### **Grid Details :**

**Tariff :** Select the Tariff you wish to use for miles rate calculation for a ship via

**Company Location :** Select the bulk location which is receiving the transport loads. (ie Distribution bulk location)

**Supplier Zip Code :** Enter the Zip code of Fuel supplier.

**Category :** Enter the inventory item category for the product being transported.

**Freight Type :** This field will determine the type of freight charge will be calculated. Select the appropriate option from the drop down list.

Amount – the freight will be a flat fee of the dollar amount entered in the Freight Amount field.

Rate – the freight will be a “per unit” rate.

Miles – the freight will be calculated on the number of miles from the terminal to the distribution bulk location site.

**Fixed Ship via :** This field will be used if the “Freight Type” field is set to the “Miles” option. Enter the Ship via to be used. If a Ship via is entered in this field, the system will use this to locate and set the Distribution (invoice) freight rate and the Receipt (Cost) freight rate. If this field is blank, the system will use the Ship via set in the Receive Transport Loads program to locate and set both the Distribution (invoice) freight rate and Receipt (Cost) freight rate.

**Freight Amount :** This field will only be used if the “Amount” option was selected in the “Freight Type” field. Enter the dollar amount to charge for freight.

**Freight Rate :** This field will only be used if the “Rate” option was selected in the “Freight Type” field. Enter the dollar amount per unit to charge for freight.

**Freight Miles :** This field will only be used if the “Miles” option was selected in the “Freight Type” field. Enter the number of miles from the terminal to the bulk location site.

**Minimum Units :** This field will only be used if the “Rate” option was selected in the “Freight Type” field. Enter the minimum number of units to be used for calculating freight charges.

#### **Pages**

[How to create records in Bulk Plant Freight](#)

[How to delete Bulk Plant Freight line item](#)