

Installing and configuring the Digiport Server device

Note: The same configuration must be done on multiple computers within the network.

Download and extract the Digiport file.



Run the **Setup64.exe**.


rk > fileserver > d\$ > PROJECTS > i21 > ScaleService > ScaleHeadInstaller > digiport

Name	Date modified	Type	Size
DgRpEncx.exe	13/10/2018 7:19 AM	Application	4,305 KB
DgRpHelp.chm	13/10/2018 7:18 AM	Compiled HTML ...	68 KB
dgrpui45.dll	13/10/2018 7:16 AM	Application extens...	2,535 KB
dgrpui4564.dll	13/10/2018 7:17 AM	Application extens...	3,587 KB
digirlpt.cat	16/10/2018 9:32 AM	Security Catalog	12 KB
DigiRIPt.sys	13/10/2018 7:17 AM	System file	187 KB
DigiRIPt64.sys	13/10/2018 7:17 AM	System file	224 KB
digirp.inf	13/10/2018 7:20 AM	Setup Information	7 KB
digirprt.inf	13/10/2018 7:20 AM	Setup Information	5 KB
mdmdgiam.cat	16/10/2018 9:32 AM	Security Catalog	9 KB
mdmdgiam.inf	13/10/2018 7:20 AM	Setup Information	16 KB
readme.txt	16/10/2018 9:51 AM	Text Document	23 KB
Setup.com	13/10/2018 7:19 AM	MS-DOS Applicati...	165 KB
Setup.exe	13/10/2018 7:19 AM	Application	165 KB
Setup32.exe	13/10/2018 7:18 AM	Application	2,291 KB
Setup64.exe	13/10/2018 7:18 AM	Application	3,112 KB

Click the **Next** button.



The Digiport device is recognize, click the **Next** button.



In the next screen, configure the COM Port Settings:

Specify the number of Ports available in the **COM Port Settings**. (In this example, we have 4 ports available)

Specify the **Starting COM** port.

Digi RealPort Setup Wizard v 4.8.488

Describe the Device

Enter information for the device you would like to use.

Device Model Name:
PortServer TS 4

Network Settings

IP MAC DNS TCP-L

192 . 168 . 0 . 48

Default Network Profile:
TCP: Typical Settings

RealPort TCP: 771 Serial UDP: 2101

Wait for COM open request

COM Port Settings

No. Ports: 4

Starting COM: COM10

Skip Modem PnP

Device Features

Encryption
 Authentication

Install Options...
Help

< Back **Finish** Cancel

Click the **Finish** button to install.




Installing Digi RealPort

Please wait while your Digi RealPort device is installed.




Preparing Digi RealPort software



< Back

Finish

Cancel



You can now open **i21 Electron** and configure the Scale Ports.

[Configuring the Scale Ports in Electron and the Scale weight reading in a Scale Ticket](#)